

「銀河」運用記録 "GINGA" Daily Report

Ver 1.5

1987 MONTH : 12 DAY : 2 Y+ 300

Written by : Dotani

OPERATION: Pointing to SN1987A (PC/MPC1 mode)

Tsushima

	[PASS 1]	[PASS 2]	[PASS 3]	[PASS 4]	[PASS 5]
NO.	871202-0204	871202-0307	871202-0411	871202-0514	871202-0618
AOS LOS	: : : :	3:30:04 3:41:51	5:11:51 5:23:57	6:54:13 7:06:05	8:36:17 8:41:36
ELMX	:	53.31 35:21	天頂 :	63.74 59:32	22.23 41:25
COMMANDS	No Contact because of Antenna Trouble (2170 SW の 接触不良)	SH REP LHV RED BC ENA-0 Φ1 C2 BC EXE ST MAP PC CLR/WRT/CHK PC STRT	SH REP BC ENA-1 Φ5Φ5DΦ79ΦΦ15 BC EXE MANV STRT PC CLR/WRT/CHK PC STRT	ST MAP ST TRK PC CLR/WRT/CHK PC STRT OG-2 EXE	SH REP ST TRK LC E1 ON LC E2 ON BC ENA-0 Φ1 Φ2 BC EXE PC CLR/WRT/CHK PC STRT
MODE		L M A P	L M A P	L M A P	L M A P
TLMS		Rep	Rep	Rep	Rep
ACS		N M	M N V		
LAC		MPC1/PC			MPC1
HV LAC ASM AGN GBU					
EVENT			Attitude Trimming	Ranging	
ST	: :	3:38:00	5:20:00	7:02:00	8:44:00
PC PLAN		1 TMS ON 3:40 9 OG-5 EXE 3:56 17 OG-6 EXE 4:12 26 OG-4 EXE 4:30 34 BIT HI 4:46 35 OG-5 EXE 4:48 41 OG-6 EXE 5:00 46 OG-3 EXE 5:10	0001 TMS ON 05:22 0006 OG-5 EXE 05:32 0015 OG-6 EXE 05:50 0029 OG-4 EXE 06:18 0034 OG-6 EXE 06:28 0046 OG-3 EXE 06:52	0001 TMS ON 07:04 0004 OG-5 EXE 07:10 0015 OG-6 EXE 07:32 0034 OG-4 EXE 08:10 0039 OG-6 EXE 08:20 0045 OG-1 EXE 08:32 0046 OG-3 EXE 08:34	0001 BIT LOW 08:46 0002 OG-5 EXE 08:48 0003 TMS ON 08:50 0018 OG-6 EXE 09:20 0033 OG-5 EXE 09:50 0070 OG-6 EXE 11:04 0079 OG-5 EXE 11:22 0277 OG-4 EXE 17:58 0282 OG-7 EXE 18:08 0283 SLEW 360 18:10 0294 OG-5 EXE 18:32 0321 OG-4 EXE 19:26 0327 OG-5 EXE 19:38 0328 BIT LOW 19:40 0344 OG-6 EXE 20:12 0352 OG-5 EXE 20:28 0389 OG-6 EXE 21:42 0404 OG-5 EXE 22:12 0438 OG-6 EXE 23:20 0455 OG-5 EXE 23:54 0487 OG-6 EXE 00:58 0508 OG-5 EXE 01:40 0513 OG-6 EXE 01:50 0514 OG-3 EXE 01:52
COMMENT	514日目リプログラムにエラーがあり(ニモ)がモ知れません。 - 昨日3日仕事は終了。帰る日がまだ早い。				
SANGLE	149.9 → 151.0	MIN.-BAT-V(EDD)	19.0 19.1	V. 19.7 19.6	